

Exam Code: 920-544

**Exam Name:** Carrier VoIP Integrated Element Mgmt

System (IEMS) Ops

Vendor: Nortel

Version: DEMO

## Part: A

- 1: Which feature is part of the alarm count panel?
- A.Alarms with a warning severity are not shown.
- B.A summary of all critical alarms may be obtained.
- C.An annotation may be made from the alarms count panel.
- D.Alarms may be acknowledged from the alarms counts panel.

**Correct Answers: B** 

- 2: Under which of the following in the topology tree is the Alarms node found?
- A.Inventory
- **B.**Performance
- C.Network Events
- D.Fault Management

**Correct Answers: D** 

- 3: Which action may be used to display the icon of the managed object that is the source of a given alarm?
- A.From the alarm popup menu, select Show Map.
- B.Double-click on the alarm and select Show Map Detail.
- C.From the alarm popup menu, select Show Managed Object.
- D.Double-click on the alarm and select Managed Object Detail.

**Correct Answers: A** 

- 4: Which of the following is true for events that are received from devices that are not part of Integrated EMS inventory database?
- A.The IEMS will temporarily add the source device to the inventory.
- B. These events have a source field value of Unrecognized Device.
- C.The IEMS application assigns these events a logkey value of IEMS601.
- D.The IEMS application will propagate these events to alarms with a minor severity.

**Correct Answers: C** 

- 5: Which protocol is used to establish an Operator Client session from the IEMS into the Multi-service Data Manager?
- A.SSH
- B.Telnet
- **C.HTTPS**
- D.SNMPv3

**Correct Answers: C** 

- 6: Which Network Element requires its GUI element manager application to be installed on the client?
- A.STORM
- **B.Call Agent**

C.ERS 8600

D.MSS 15000

## **Correct Answers: C**

- 7: Which statement is true for performing IEMS application upgrades in a dual server (HA) environment?
- A.During the upgrade, neither server is in service.
- B.The upgrade must first be performed on the active server.
- C.A failover must not be performed until both servers are upgraded.
- D.Upgrades are performed on the standby server, while the active server is in service.

**Correct Answers: D** 

- 8: How many simultaneous sessions of each of the four supported Northbound fault streams are supported?
- A.2
- **B.4**
- C.6
- D.8

**Correct Answers: C** 

- 9: Which two must be provisioned on the IEMS in order to set up a Northbound SNMP fault stream? (Choose two.)
- A.the directory of the SNMP trap destination host (Managerdir)
- B.the MAC address of the SNMP trap destination (Managermac)
- C.the IP address of the SNMP trap destination host (Managerhost)
- D.the port number of the SNMP trap destination host (Managerport)

**Correct Answers: C D** 

- 10: Which Servman command can be issued to start the IEMS server application?
- A.start IEMS
- **B.servstart IEMS**
- C.startserv IEMS
- D.servman start IEMS

**Correct Answers: B**